

TAM 1.6 Release – Please read prior to installing TAM 1.6:

1. Please close out all other programs prior to installing TAM 1.6 Release.
2. Some companies have security features and restrictions in place on company laptops. It may be necessary for you to obtain administrative rights over the security on your computer, or you may need to have your IT department install TAM so they may override or disable security restrictions.
3. After installing TAM 1.6, plug in the Base Station and update the firmware when prompted. Once the Base Station is updated, turn on one sensor at a time and update the firmware on each sensor individually when prompted. **Do not turn all sensors on at the same time for the initial firmware update.**
4. Data sets acquired with TAM 1.6 cannot be opened by previous versions of TAM (i.e. TAM 1.4).
5. Please make sure all individuals who will be viewing data acquired or previously opened with TAM 1.6 update to the latest version.
6. Please contact Echometer with any questions.
7. Please report any problems or concerns with TAM 1.6 installation and use. TAM 1

(((ECHOMETER)))